
## Tramex Meters App - Getting Started



#### **Download**

**Download the Tramex Meters App** from the App Store or Google Play.


This app uses your phone's Bluetooth to view data from your Tramex device, so please ensure that Bluetooth is switched on.

### Register

**Register** (in-app) to create an account.

To complete your account setup, **verify your email address** with the verification link.





## Power Up


Power up your Tramex device and ensure Bluetooth is switched on.


Your your meter will pop up on the phone screen.

Tap on the meter to view the readings on-screen.

### **View Live Readings**

With the meter selected, you can view the live sensor readings in various forms.





### Register

Register your device to make best use of our cloud platform.

Select the meter, tap the "View online" button and "Tap to register".

## Tramex Meters App - Moisture Mapping



## Moisture Mapping

Ensure you are online and select 'Moisture Mapping" from the Menu options.


## Create a Report


Reports are a collection of one or more moisture maps, allowing you to group moisture maps of walls, floors, ceilings or flat roofs in one place.

Enter your report name and location.

If you're on-site and you don't know your address, tap the geotag icon and your location will be found.

Click 'create' to proceed.





#### Create a Surface

Add the first surface to your report, you can have as many surfaces as you like.


Give your surface a name and tap the icon to select or take a photo. This image will become the background of your surface map. You can select a photo from your library or take a new picture.


## Select Your Moisture Map

You are all setup and ready to start adding readings with your meter.

Switch on your Tramex meter and ensure that Bluetooth is enabled.

Select the Moisture Map you have created.







## ChooseYour Device

Tap the devices button and select your meter from the list.

# Saving Readings Choose the cell you want to start with on your grid. Take

your measurement and tap on your device to save the reading.

To fill up the grid, select the cells by tapping them or swipe

on your device reading. The cell selection moves in the direction that you swipe. If you need more detail in particular areas because you've found moisture, you can adjust the grid density at any time and enter more readings.

The grid can be made fullscreen if needed.







# Grid Colour Adjustment When you've entered your readings, you may like to highlight

the lowest and/ or highest readings in the grid, by modifying the 'grid colour adjustment thresholds'.


This acts like a traffic light system, so that the readings are

easier to interpret.

# Exporting your Data When your surface reading is complete, you can export the

image for a list of readings by hitting one of the buttons above.

As this is the Tramex cloud system, you can open this surface report in your browser on any device, laptop or tablet.



www.tramexmeters.com